The Input Method Protocol

X Consortium Standard

Masahiko Narita, FUJITSU Limited.
Hideki Hiura, SunSoft, Inc.

X Version 11, Release 7.7

Version 1.0

Abstract

[illegible]

Table of Contents

Introduction

Scope

[illegible]

[illegible]

[illegible]

[illegible]

Background

[illegible]

[illegible]

[illegible]

[illegible]

Input Method Styles

Architecture

Implementation Model

Structure of IM

[illegible]

[illegible]

[illegible]

[illegible]

[illegible]

[illegible]

[illegible]

Event Handling Model

[illegible]

[illegible]

BackEnd Method

[illegible]

[illegible]

FrontEnd Method

[illegible]

[illegible]



[illegible]

Event Flow Control

[illegible]

[illegible]

[illegible]

[illegible]

[illegible] XIM_REGISTER_TRIGGERKEYS [illegible]

[illegible]

Default Preconnection Convention

[illegible] XIM_SERVERS, [illegible]

[illegible] TRANSPORT, [illegible] LOCALES, [illegible]

[illegible] XIM_SERVERS [illegible]

[illegible] TRANSPORT [illegible]

[illegible]

Protocol

[illegible]

Basic Requests Packet Format

[illegible]

[illegible]

```
major-opcode:            CARD8
minor-opcode:            CARD8
length:                  CARD16
```

[illegible] XIM_QUERY_EXTENSION [illegible]

Data Types

[illegible]

```
BITMASK16
     CARD16
BITMASK32
     CARD32
PADDING FORMAT
     Where N is some expression, and Pad(N) is the number of bytes needed to round N up to a

          Pad(N) = (4 - (N mod 4)) mod 4

LPCE
  1          A character from the4 X Portable Character Set in Latin Portable
             Character Encoding

STRING
     2     n              length of string in bytes
     n     LISTofLPCE     string
     p                    unused, p=Pad(2+n)

STR
     1     n              length of name in bytes
     n     STRING8        name

XIMATTR
     2     CARD16         attribute ID (*1)
     2     CARD16         type of the value (*2)
     2     n              length of im-attribute
     n     STRING8        im-attribute
     p                    unused, p = Pad(2+n)
```

The im-attribute argument specifies XIM values such as XNQueryInputStyle.

```
XICATTR
     2     CARD16         attribute ID (*1)
     2     CARD16         type of the value (*2)
     2     n              length of ic-attribute
     n     STRING8        ic-attribute
     p                    unused, p = Pad(2+n)
```

(*1) XIMATTR and XICATTR are used during the setup stage and XIMATTRIBUTE and XICATTRIBUTE are used after each attribute ID has been recognized by the IM Server and the IM library.

(*2) The value types are defined as follows:

□□□□ □□□	□□□□	□□□□□□
PK	□□□□□□□□□□□□□ <□□□□□□?□□□	□□□□□□+Q(-
P&	□□□□□□□□□□	$458N
PE	□□□□□□□□□□	$458&H
P(	□□□□□□□□□□	$458(E
P)	□□□□□□□□□□	□"56<@N

PF	3	$458(E		
P&K	*6	E		 *6
Y	Y	E	Y	
Y	Y		$458(E	*6
P&&	*5	E	6<"&H	*
Y	Y	E	6<"&H	=
Y	Y	E	$458&H	
Y	Y	E	$458&H	
P&E	*	E	6<"&H	*
Y	Y	E	6<"&H	=
P&(	*	E		A
Y	Y		"56<@N	A
Y	Y		Y	R +ES-
P&F	*6 0>"	)		 *6 "56@ @15>1=+Q)-
Y	Y		*6 "56@ @15>1=	*6 0!"
Y	Y		*6 02">1= "4"1	0>
P&O	*6 $	*6 "5$2<7 "1*"	Y	Y
P&N	*6	*6 51186" "4"1		
P&'	*6 5	*6 511""4"1		
P#O	<?			

```
(*3)  The IC value for the separator of NestedList is defined as follows,
            #define   XNSeparatorofNestedList   "separatorofNestedList"
      , which is registered in X Consortium and cannot be used for any other purpose.

(*4) LISTofFOO
            A Type name of the form LISTof FOO means a counted list of elements of type FOO.
            The size of the length field may vary (it is not necessarily the same
            size as a FOO), and in some cases, it may be implicit.
XIMTRIGGERKEY
     4     CARD32        keysym
     4     CARD32        modifier
     4     CARD32        modifier mask
```

```
ENCODINGINFO
     2     n            length of encoding info
     n     STRING8      encoding info
     p                  unused, p=Pad(2+n)


     1     CARD8        extension major-opcode
     1     CARD8        extension minor-opcode
     2     n            length of extension name
     n     STRING8      extension name
     p                  unused, p = Pad(n)

XIMATTRIBUTE
     2     CARD16       attribute ID
     2     n            value length
     n                  value
     p                  unused, p = Pad(n)

XICATTRIBUTE
     2     CARD16       attribute ID
     2     n            value length
     n                  value
     p                  unused, p = Pad(n)



XIMSTRCONVTEXT
     2    CARD16                      XIMStringConversionFeedback
          #x0000001                   XIMStringConversionLeftEdge
          #x0000002                   XIMStringConversionRightEdge
          #x0000004                   XIMStringConversionTopEdge
          #x0000008                   XIMStringConversionBottomEdge
          #x0000010                   XIMStringConversionConvealed
          #x0000020                   XIMStringConversionWrapped
     2     n                          byte length of the retrieved string
     n     STRING8                    retrieved string
     p                                unused, p = Pad(n)
     2     m                          byte length of feedback array
     2                                unused
     m     LISTofXIMSTRCONVFEEDBACK   feedback array(*1)

(*1)   This field is reserved for future use.

XIMFEEDBACK
     4    CARD32       XIMFeedback
          #x000001     XIMReverse
          #x000002     XIMUnderline
          #x000004     XIMHighlight
          #x000008     XIMPrimary
          #x000010     XIMSecondary
          #x000020     XIMTertiary
          #x000040     XIMVisibleToForward
          #x000080     XIMVisibleToBackward
          #x000100     XIMVisibleCenter
```

```
XIMHOTKEYSTATE
     4    CARD32       XIMHotKeyState
          #x0000001    XIMHotKeyStateON
          #x0000002    XIMHotKeyStateOFF

XIMPREEDITSTATE
     4    CARD32       XIMPreeditState
          #x0000001    XIMPreeditEnable
          #x0000002    XIMPreeditDisable

XIMRESETSTATE
     4    CARD32       XIMResetState
          #x0000001    XIMInitialState
          #x0000002    XIMPreserveState
```

Error Notification

[illegible] XIM_ERROR [illegible]

[illegible]

```
XIM_ERROR (IM Server <--> IM library)

          2     CARD16          input-method-ID
          2     CARD16          input-context-ID
          2     BITMASK16       flag (*1)
                #0000           Both Input-Method-ID and Input-Context-ID are invalid
                #0001           Input-Method-ID is valid
                #0002           Input-Context-ID is valid
          2     CARD16          Error Code
                #1              BadAlloc
                #2              BadStyle
                #3              BadClientWindow
                #4              BadFocusWindow
                #5              BadArea
                #6              BadSpotLocation
                #7              BadColormap
                #8              BadAtom
                #9              BadPixel
                #10             BadPixmap
                #11             BadName
                #12             BadCursor
                #13             BadProtocol
                #14             BadForeground
                #15             BadBackground
                #16             LocaleNotSupported
                #999            BadSomething (*2)
          2     n               byte length of error detail.
          2     CARD16          type of error detail (*3)
```

```
          n     STRING8         error detail (*4)
          p                     unused, p = Pad(n)

(*1)  Before an IM is created, both Input-Method-ID and
      Input-Context-ID are invalid.
      Before an IC is created, only Input-Method-ID is valid.
      After that, both of Input-Method-ID and Input-Context-ID are valid.

(*2) Unspecific error, for example "language engine died"

(*3) This field is reserved for future use.

(*4) Vendor defined detail error message
```

Connection Establishment

XIM_CONNECT [illegible]

```
XIM_CONNECT (IM library -> IM Server)
     1                     byte order
           #x42            MSB first
           #x6c            LSB first
     1                     unused
     2     CARD16          client-major-protocol-version (*1)
     2     CARD16          client-minor-protocol-version (*1)
     2     CARD16          number of client-auth-protocol-names
     n     LISTofSTRING    client-auth-protocol-names

(*1) Specify the version of IM Protocol that the client supports.
```

[illegible] XIM_CONNECT [illegible]

XIM_AUTH_REQUIRED [illegible]

```
XIM_AUTH_REQUIRED (IM library <--> IM Server)

     1     CARD8             auth-protocol-index
     3                       unused
     2     n                 length of authentication data
     2                       unused
     n     <varies>     data
     p                       unused, p = Pad(n)
```

[illegible] XIM_CONNECT [illegible] XIM_AUTH_SETUP [illegible]

[illegible] XIM_AUTH_REPLY [illegible] XIM_AUTH_REQUIRED [illegible]

```
XIM_AUTH_REPLY (IM library -> IM Server)
     2     n                 length of authentication data
     2                       unused
     2     n                 length of authentication data
     2                       unused
     n     <varies>      data
     p                       unused, p = Pad(n)
```

"

XIM_AUTH_NEXT C

```
XIM_AUTH_NEXT (IM library <--> IM Server)
     2     n                 length of authentication data
     2                       unused
     n     <varies>      data
     p                       unused, p = Pad(n)
```

"

"6 XIM_AUTH_SETUP

```
XIM_AUTH_SETUP (IM Server -> IM library)
     2     CARD16           number of client-auth-protocol-names
     2                      unused
     n     LISTofSTRING     server-auth-protocol-names
```

"

XIM_AUTH_NGC

*6 J4;"0J<@+6 TU6 -

"6 XIM_CONNECT_REPLYXIM_CONNECT XIM_AUTH_REQUIRED

```
XIM_CONNECT_REPLY (IM Server -> IM library)
     2     CARD16     server-major-protocol-version (*1)
     2     CARD16     server-minor-protocol-version (*1)
```

(*1) Specify the version of IM Protocol that the IM Server supports.
This document specifies major version one, minor version zero.

06

/ ;BU

<BU

/ XIM_CONNECT

6□□ □□U□

6□□ □□ □□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□U

/ 5□□□□□□XIM_AUTH_REQUIRED□□U□

5□□□□□□□T□□□□□U□□U□

/ 6□□□□□□□□□□□□□□□□□□□□□□□□□□XIM_AUTH_REPLY□□U□

6□□□□□□□□□□□□□□□□□□□□XIM_AUTH_NEXT□□U□

6□□□□□□□□□□□□□□□□□□□XIM_AUTH_NG□□U□□□□□□□□□□□□□□□□□□□□□□□□□□□□

/ 5□□□□□□XIM_CONNECT_REPLY□□U□□□□□□□□□5□□□□XIM_AUTH_SETUP
□U□

5□□□□□□XIM_AUTH_NEXT□□U□

5□□□□□□XIM_AUTH_NG□□U□□□□□□□□□□□□□□□□□□□□□□□□□□□□

5□□□□□□□T□□□□□U□□U□

/ □□□□□XIM_AUTH_REQUIRED□□U□

/ □□□□□XIM_AUTH_NG□□U□□□□□□□□□□□□□□□□□□□□□□□□□□□□

□□□□□□□□□□□□□□□□□□□□□□□□□□□□6 □□□□□□□

/ ;□□□□□□□□□□□B□□□□□□□□□□□□□□□□□U□

<□□□□□□□□□□□□□□□B□□□□□□□□□□□□□□□□□U□

/ 5□□□□□□XIM_CONNECT

□U□ □5□□□□□□□T□□□□□U□□U□

/ 6□□ □□□□□□XIM_AUTH_REQUIRED□□U□

6□□ □ □□□□ □□ □□□□XIM_AUTH_SETUP□ □U

6□□ □□□□□ □□□□□XIM_CONNECT_REPLY
□U□□□□□□□□

/ 5□□□□□□XIM_AUTH_REPLY□□U□

5□□□□□□XIM_AUTH_NEXT□□U□

5□□□□□□□T□□□□□U□□U□

□□□□□XIM_AUTH_REQUIRED□□U□

6□□ □□□□□□XIM_AUTH_SETUP□□U□

6□□ □□□□□□XIM_CONNECT_REPLY □□U□□□□□□□□

5XIM_AUTH_REQUIREDU

5TU U

6XIM_CONNECT_REPLYU

6XIM_AUTH_NGU

6XIM_AUTH_NEXTU

XIM_AUTH_NGU

XIM_DISCONNECT C

*6 J86$2<<1$"+6 U6 -

XIM_DISCONNECTC"6 XIM_DISCONNECT_REPLY!XIM_ERROR!

*6 J86$2<<1$"J51?=+6 U6 -

XIM_OPENC6 6

```
XIM_OPEN (IM library -> IM Server)
     n     STR     locale name
     p             unused, p = Pad(n)
```

XIM_OPENC"6 XIM_OPEN_REPLY!XIM_ERROR !

```
XIM_OPEN_REPLY (IM Server -> IM library)
     2     CARD16             input-method-ID
     2     n                  byte length of IM attributes supported
     n     LISTofXIMATTR      IM attributes supported
     2     m                  byte length of IC attributes supported
     2     CARD16             unused
     m     LISTofXICATTR      IC attributes supported
```

XIM_OPEN_REPLY6 6$?6"*6 4""5?6"*6$4""5"6 6$68 !6 6 !6 .6$ #"6 6 6 .6$ *"6$<? ?6"*6$4""5

XIM_CLOSE C6 6

```
XIM_CLOSE (IM library -> IM Server)
```

```
     2     CARD16     input-method-ID
     2                unused
```

XIM_CLOSE [illegible] C [illegible] " [illegible] 6 [illegible] XIM_CLOSE_REPLY [illegible] ! [illegible] XIM_ERROR [illegible] ! [illegible]

```
XIM_CLOSE_REPLY (IM Server -> IM library)
     2     CARD16     input-method-ID
     2                unused
```

Event Flow Control

4 [illegible] 6 [illegible] XIM_SET_EVENT_MASK [illegible] 6 [illegible] 6 [illegible] 6 [illegible] G [illegible] 6 [illegible] 6 [illegible] 6 [illegible] ! [illegible] * [illegible] B [illegible] 6 [illegible]

```
XIM_SET_EVENT_MASK (IM Server -> IM library)
     2     CARD16        input-method-ID
     2     CARD16        input-context-ID
     4     EVENTMASK     forward-event-mask (*1)
     4     EVENTMASK     synchronous-event-mask (*2)

(*1)  Specify all the events to be forwarded to the IM Server by the IM library.
(*2)  Specify the events to be forwarded with synchronous flag on by the IM library.
```

XIM_SET_EVENT_MASK [illegible] C [illegible] " [illegible] ! [illegible] XIM_SET_EVENT_MASK [illegible] 6 [illegible] # [illegible] 68 [illegible] B [illegible] 68 [illegible] ! [illegible] C [illegible] " [illegible] 6$G [illegible]

; [illegible] 8 [illegible] 1 [illegible] 6 [illegible] XIM_REGISTER_TRIGGERKEYS [illegible] 6 [illegible] XIM_OPEN_REPLY [illegible] 2 [illegible] 6 [illegible] 6 [illegible] 1 [illegible]

```
XIM_REGISTER_TRIGGERKEYS (IM Server -> IM library)

     2     CARD16                   input-method-ID
     2                              unused
     4     n                        byte length of on-keys
     n     LISTofXIMTRIGGERKEY      on-keys list
     4     m                        byte length of off-keys
     m     LISTofXIMTRIGGERKEY      off-keys list
```

XIM_REGISTER_TRIGGERKEYS [illegible] C [illegible] " [illegible] 6 [illegible] 6 [illegible] ! [illegible] ! [illegible]

" [illegible] 6 [illegible] 6 [illegible] XIM_TRIGGER_NOTIFY [illegible] ! [illegible] ! [illegible] ! [illegible]

```
XIM_TRIGGER_NOTIFY (IM library -> IM Server)
     2     CARD16           input-method-ID
     2     CARD16           input-context-ID
     4     CARD32           flag
           #0               on-keys list
           #1               off-keys list
     4     CARD32           index of keys list
     4     EVENTMASK        client-select-event-mask (*1)

(*1)  Specify the events currently selected by the IM library with XSelectInput.
```

XIM_TRIGGER_NOTIFY [illegible]C[illegible]"[illegible]6 [illegible] XIM_TRIGGER_NOTIFY_REPLY[illegible]![illegible]XIM_ERROR[illegible]![illegible]

```
XIM_TRIGGER_NOTIFY_REPLY (IM Server -> IM library)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

Encoding Negotiation

XIM_ENCODING_NEGOTIATION[illegible]C[illegible]3[illegible]![illegible]$[illegible]1[illegible]

```
XIM_ENCODING_NEGOTIATION (IM library -> IM Server).sp 6p
     2     CARD16                 input-method-ID
     2     n                      byte length of encodings listed by name
     n     LISTofSTR              list of encodings supported in the IM library.
     p                            unused, p = Pad(n)
     2     m                      byte length of encodings listed by detailed data
     2                            unused
     m     LISTofENCODINGINFO     list of encordings supported in the IM library
```

"[illegible]6 [illegible]6[illegible]6[illegible]#[illegible]&[illegible]![illegible]"[illegible] XIM_OPEN[illegible]*2[illegible]6 +-[illegible]"[illegible] *[illegible]$[illegible]

XIM_ENCODING_NEGOTIATION[illegible]C[illegible]"[illegible]6 [illegible] XIM_ENCODING_NEGOTIATION_REPLY[illegible]![illegible] XIM_ERROR[illegible]![illegible]

```
XIM_ENCODING_NEGOTIATION_REPLY (IM Server -> IM library)
     2     CARD16     input-method-ID
     2     CARD16     category of the encoding determined.
           #0         name
           #1         detailed data
     2     INT16      index of the encoding determinated.
```

```
     2               unused
```

Query the supported extension protocol list

XIM_QUERY_EXTENSION [illegible]

```
XIM_QUERY_EXTENSION (IM library -> IM Server)
     2     CARD16        input-method-ID
     2     n             byte length of extensions supported by the IM library
     n     LISTofSTR     extensions supported by the IM library
     p                   unused, p = Pad(n)
```

[illegible] XIM_OPEN [illegible]

[illegible]

[illegible]

[illegible] XIM_QUERY_EXTENSION [illegible] BadProtocol [illegible] BadProtocol [illegible]

XIM_QUERY_EXTENSION [illegible] XIM_QUERY_EXTENSION_REPLY [illegible] XIM_ERROR [illegible]

```
XIM_QUERY_EXTENSION_REPLY (IM Server -> IM library)
     2     CARD16      input-method-ID
     2     n           byte length of extensions supported by both the IM library and the IM S
     n     LISTofEXT   list of extensions supported by both the IM library and the IM Server
```

XIM_QUERY_EXTENSION_REPLY [illegible] XIM_QUERY_EXTENSION [illegible]

[illegible]

Setting IM Values

XIM_SET_IM_VALUES [illegible]

```
XIM_SET_IM_VALUES (IM library -> IM Server)
     2     CARD16                  input-method-ID
     2     n                       byte length of im-attribute
```

```
     n     LISTofXIMATTRIBUTE     im-attributes
```

[illegible] XIM_SET_IM_VALUES [illegible] XIM_OPEN_REPLY [illegible]

XIM_SET_IM_VALUES [illegible] XIM_SET_IM_VALUES_REPLY [illegible] XIM_ERROR [illegible] XIM_ERROR [illegible]

```
XIM_SET_IM_VALUES_REPLY (IM Server -> IM library)
     2     CARD16     input-method-ID
     2                unused
```

XIM_SET_IM_VALUES_REPLY [illegible]

Getting IM Values

XIM_GET_IM_VALUES [illegible]

```
XIM_GET_IM_VALUES (IM library -> IM Server)
     2     CARD16           input-method-ID
     2     n                byte length of im-attribute-id
     n     LISTofCARD16     im-attribute-id
     p                      unused, p=Pad(n)
```

XIM_GET_IM_VALUES [illegible] XIM_GET_IM_VALUES_REPLY [illegible] XIM_ERROR [illegible]

```
XIM_GET_IM_VALUES_REPLY (IM Server -> IM library)
     2     CARD16                 input-method-ID
     2     n                      byte length of im-attributes returned
     n     LISTofXIMATTRIBUTE     im-attributes returned
```

[illegible] XIM_GET_IM_VALUES_REPLY [illegible] XIM_GET_IM_VALUES [illegible]

Creating an IC

XIM_CREATE_IC [illegible]

```
XIM_CREATE_IC (IM library -> IM Server)
     2     CARD16                 input-method-ID
     2     n                      byte length of ic-attributes
     n     LISTofXICATTRIBUTE     ic-attributes
```

[illegible] XIM_CREATE_IC [illegible]

XIM_CREATE_IC [illegible] C [illegible] #[illegible]68[illegible]"[illegible] 6 [illegible] XIM_CREATE_IC_REPLY [illegible]![illegible] XIM_ERROR [illegible]![illegible]

```
XIM_CREATE_IC_REPLY (IM Server -> IM library)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

Destroying the IC

XIM_DESTROY_IC [illegible] C [illegible] 6$[illegible]

```
XIM_DESTROY_IC (IM library -> IM Server)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

XIM_DESTROY_IC [illegible] C [illegible] "[illegible] 6 [illegible] XIM_DESTROY_IC_REPLY [illegible] XIM_DESTROY_IC [illegible] $[illegible]![illegible]![illegible] XIM_PREEDIT_DRAW [illegible] XIM_PREEDIT_DONE.

```
XIM_DESTROY_IC_REPLY (IM Server -> IM library)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

Setting IC Values

XIM_SET_IC_VALUES [illegible] C [illegible] 6$[illegible]

```
XIM_SET_IC_VALUES (IM library -> IM Server)
     2     CARD16                 input-method-ID
     2     CARD16                 input-context-ID
     2     n                      byte length of ic-attributes
     2                            unused
     n     LISTofXICATTRIBUTE     ic-attributes
```

"[illegible] XIM_SET_IC_VALUES [illegible]?6[illegible]"[illegible]*6$4"[illegible] "56A;"1[illegible] 4[illegible] XIM_OPEN_REPLY [illegible]

XIM_SET_IC_VALUES [illegible] C [illegible] "[illegible] 6 [illegible] XIM_SET_IC_VALUES_REPLY [illegible]![illegible] XIM_ERROR [illegible]![illegible] XIM_ERROR [illegible]

```
XIM_SET_IC_VALUES_REPLY (IM Server -> IM library)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

Getting IC Values

XIM_GET_IC_VALUES [illegible] C [illegible] C [illegible] 6$ [illegible] 6 [illegible]

```
XIM_GET_IC_VALUES (IM library -> IM Server)

     2     CARD16           input-method-ID
     2     CARD16           input-context-ID
     2     n                byte length of ic-attribute-id
     n     LISTofCARD16     ic-attribute-id
     p                      unused, p=Pad(2+n)
```

6[illegible]?6[illegible]"[illegible]$458&H [illegible] < [illegible] ? [illegible]

XIM_GET_IC_VALUES [illegible] C [illegible] " [illegible] 6 [illegible] XIM_GET_IC_VALUES_REPLY [illegible] ! [illegible] XIM_ERROR [illegible] ! [illegible]

```
XIM_GET_IC_VALUES_REPLY (IM Server -> IM library)
     2     CARD16                 input-method-ID
     2     CARD16                 input-context-ID
     2     n                      byte length of ic-attribute
     2                            unused
     n     LISTofXICATTRIBUTE     ic-attribute
```

Setting IC Focus

XIM_SET_IC_FOCUS [illegible] C [illegible] 6$ [illegible]

```
XIM_SET_IC_FOCUS (IM library -> IM Server)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

XIM_SET_IC_FOCUS [illegible] C [illegible]

Unsetting IC Focus

XIM_UNSET_IC_FOCUS [illegible] C [illegible] 6$ [illegible]

```
XIM_UNSET_IC_FOCUS (IM library -> IM Server)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

XIM_UNSET_IC_FOCUS [illegible] C [illegible]

Filtering Events

1 [illegible] A [illegible] ! 1 [illegible] * [illegible]

*[illegible]1[illegible]XIM_FORWARD_EVENT[illegible]"[illegible]6[illegible]C[illegible]XIM_SYNC_REPLY[illegible]![illegible]C[illegible]

[illegible]A[illegible]!1[illegible]

3[illegible] A[illegible]!1[illegible]B[illegible]![illegible] XIM_SET_EVENT_MASK[illegible]2[illegible]

6[illegible] 6 [illegible] XIM_FORWARD_EVENT[illegible]XIM_COMMIT[illegible]C[illegible]4[illegible]6 [illegible]6 [illegible]XIM_FORWARD_EVENT[illegible]6 [illegible]6 [illegible]XIM_FORWARD_EVENT[illegible]XIM_COMMIT[illegible]6 [illegible]6[illegible]6 [illegible]![illegible]C[illegible]6 [illegible]C[illegible]6[illegible]6 [illegible]XIM_FORWARD_EVENT[illegible]6 [illegible]0[illegible]6 [illegible]

6[illegible]6 [illegible]XIM_FORWARD_EVENT[illegible]6 [illegible]C[illegible]"[illegible]6 [illegible]XIM_FORWARD_EVENT[illegible]XIM_SYNC_REPLY[illegible]6[illegible]XIM_FORWARD_EVENT[illegible]XIM_COMMIT[illegible]6 [illegible]A[illegible]B[illegible]XIM_SYNC_REPLY[illegible]

[illegible]![illegible]



[illegible]

[illegible]#[illegible]![illegible]![illegible]



[illegible]

```
XIM_FORWARD_EVENT (IM library <--> IM Server)
     2     CARD16         input-method-ID
     2     CARD16         input-context-ID
     2     BITMASK16      flag
           #0001          synchronous
           #0002          request filtering (*1)
           #0004          request lookupstring (*2)
     2     CARD16         serial number
           XEVENT         X event
```

(*1) Indicate the receiver should filter events and possible preedit may be invoked.

(*2) Indicate the receiver should only do lookup string. The IM Server is expected to just do a conversion of the key event to the best candidate. This bit may affect the state of the preedit state (e.g. compose of dead key sequences).

[illegible]

XIM_FORWARD_EVENT [illegible] XIM_FORWARD_EVENT [illegible]

[illegible]

Synchronizing with the IM Server

XIM_SYNC [illegible]

```
XIM_SYNC (IM library <--> IM Server)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

[illegible] XIM_SYNC [illegible]

```
XIM_SYNC_REPLY (IM Server <--> IM library)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

[illegible] XIM_FORWARD_EVENT, [illegible] XIM_COMMIT [illegible] XIM_SYNC_REPLY [illegible]

Sending a committed string

[illegible] XIM_COMMIT [illegible]

```
XIM_COMMIT (IM Server -> IM library)

     2     CARD16          input-method-ID
     2     CARD16          input-context-ID
     2     BITMASK16       flag
           #0001           synchronous
           #0002           XLookupChars
           #0004           XLookupKeySym
           #0006           XLookupBoth = XLookupChars | XLookupKeySym
```

[illegible]

```
     2                unused
     4     KEYSYM     KeySym
```

[illegible]

```
     2     m               byte length of committed string
     m     LISTofBYTE      committed string
     p                     unused, p = Pad(m)
```

[illegible]

```
     2                    unused
     4     KEYSYM         KeySym
     2     n              byte length of committed string
     n     LISTofBYTE     committed string
     p                    unused, p = Pad(2+n)
```

"[illegible]6 [illegible]XIM_COMMIT[illegible]

Reset IC

XIM_RESET_IC[illegible]C[illegible]6$[illegible]6 [illegible]

```
XIM_RESET_IC (IM library -> IM Server)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

XIM_RESET_IC[illegible]C[illegible]"[illegible]6 [illegible]XIM_RESET_IC_REPLY[illegible]![illegible]XIM_ERROR[illegible]![illegible]

```
XIM_RESET_IC_REPLY (IM Server -> IM library)

     2     CARD16         input-method-ID
     2     CARD16         input-context-ID
     2     n              byte length of preedit string
     n     LISTofBYTE     preedit string
     p                    unused, p = Pad(2+n)
```

XIM_RESET_IC_REPLY [illegible]#[illegible]68[illegible]6$[illegible]

Callbacks

6[illegible]*6 [illegible]*6 [illegible]4[illegible]*6 [illegible]4[illegible]*6 @[illegible]$[illegible]![illegible]*6 [illegible]$[illegible]![illegible].[illegible]*6 [illegible]$[illegible]![illegible]![illegible]

4[illegible]![illegible]C[illegible]6 [illegible]6 [illegible]C[illegible]6 [illegible]6 [illegible]

3[illegible]6 [illegible]![illegible]C[illegible]C[illegible]6 [illegible]6 [illegible]C[illegible]

Negotiating geometry

"[illegible]6 [illegible]XIM_GEOMETRY [illegible]*6 [illegible]*6 [illegible]4[illegible]*6 [illegible]4[illegible]

```
XIM_GEOMETRY (IM Server -> IM library)
```

```
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

"[illegible]3[illegible]6$[illegible]

Converting a string

```
XIM_STR_CONVERSION (IM Server -> IM library)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
     2     CARD16     XIMStringConversionPosition
     2                unused
     4     CARD32     XIMCaretDirection
           #0         XIMForwardChar
           #1         XIMBackwardChar
           #2         XIMForwardWord
           #3         XIMBackwardWord
           #4         XIMCaretUp
           #5         XIMCaretDown
           #6         XIMNextLine
           #7         XIMCPreviousLine
           #8         XIMLineStart
           #9         XIMLineEnd
           #10        XIMAbsolutePosition
           #11        XIMDontChange
     2     CARD16     factor
     2     CARD16     XIMStringConversionOperation
           #0001      XIMStringConversionSubstitution
           #0002      XIMStringConversionRetrieval
     2     INT16      byte length to multiply the XIMStringConversionType
```

`XIM_STR_CONVERSION` [illegible] 6 [illegible]

```
XIM_STR_CONVERSION_REPLY (IM library -> IM Server)

     2     CARD16             input-method-ID
     2     CARD16             input-context-ID
     4     CARD32             XIMStringConversionFeedback
           XIMSTRCONVTEXT     XIMStringConversionText
```

`XIM_STR_CONVERSION_REPLY` [illegible]![illegible]

Preedit Callbacks

"[illegible]6 [illegible] `XIM_PREEDIT_START` [illegible]*6 [illegible] $[illegible]![illegible]

```
XIM_PREEDIT_START (IM Server -> IM library)
```

```
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

[illegible]

```
XIM_PREEDIT_START_REPLY (IM library -> IM Server)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
     4     INT32     return value
```

XIM_PREEDIT_START_REPLY [illegible]

[illegible] XIM_PREEDIT_DRAW [illegible]

```
XIM_PREEDIT_DRAW (IM Server -> IM library)

     2     CARD16                input-method-ID
     2     CARD16                input-context-ID
     4     INT32                 caret
     4     INT32                 chg_first
     4     INT32                 chg_length
     4     BITMASK32             status
           #x0000001             no string
           #x0000002             no feedback
     2     n                     length of preedit string
     n     STRING8               preedit string
     p                           unused, p = Pad(2+n)
     2     m                     byte length of feedback array
     2                           unused
     m     LISTofXIMFEEDBACK     feedback array
```

[illegible]

[illegible] XIM_PREEDIT_CARET [illegible]

```
XIM_PREEDIT_CARET (IM Server -> IM library)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
     4     INT32      position
     4     CARD32     direction
           #0         XIMForwardChar
```

```
             #1          XIMBackwardChar
             #2          XIMForwardWord
             #3          XIMBackwardWord
             #4          XIMCaretUp
             #5          XIMCaretDown
             #6          XIMNextLine
             #7          XIMCPreviousLine
             #8          XIMLineStart
             #9          XIMLineEnd
             #10         XIMAbsolutePosition
             #11         XIMDontChange
       4     CARD32      style
             #0          XIMInvisible
             #1          XIMCPrimary
             #2          XIMSecondary
```

[illegible]

```
XIM_PREEDIT_CARET_REPLY (IM library -> IM Server)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
     4     CARD32     position
```

[illegible]

[illegible] XIM_PREEDIT_DONE [illegible]

```
XIM_PREEDIT_DONE (IM Server -> IM library)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

Preedit state notify

```
XIM_PREEDITSTATE (IM Server -> IM Library)
     2     CARD16        input-method-ID
     2     CARD16        input-context-ID
     4     BITMASK32     XIMPreeditState
           #x0000000     XIMPreeditUnknown
           #x0000001     XIMPreeditEnable
           #x0000002     XIMPreeditDisable
```

XIM_PREEDITSTATE [illegible]

Status Callbacks

[illegible] XIM_STATUS_START [illegible]

```
XIM_STATUS_START (IM Server -> IM library)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

[illegible] XIM_STATUS_DRAW [illegible]

```
XIM_STATUS_DRAW (IM Server -> IM library)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
     4     CARD32     type
           #0         XIMTextType
           #1         XIMBitmapType
```

[illegible]

```
     4     BITMASK32            status
           #x0000001            no string
           #x0000002            no feedback
     2     n                    length of status string
     n     STRING8              status string
     p                          unused, p = Pad(2+n)
     2     m                    byte length of feedback array
     2                          unused
     m     LISTofXIMFEEDBACK    feedback array
```

[illegible]

```
     4     PIXMAP     pixmap data
```

[illegible]

[illegible] XIM_STATUS_DONE [illegible]

```
XIM_STATUS_DONE (IM Server -> IM library)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

Acknowledgements

[illegible]

[illegible]

[illegible]

References

[illegible]

[illegible]

A. Common Extensions

[illegible] XIM_EXT_SET_EVENT_MASK [illegible]

[illegible]

XIM_EXT_SET_EVENT_MASK [illegible]

```
XIM_EXT_SET_EVENT_MASK (IM Server -> IM library)

     2     CARD16        input-method-ID
     2     CARD16        input-context-ID
     4     EVENTMASK     filter-event-mask (*1)
     4     EVENTMASK     intercept-event-mask (*2)
     4     EVENTMASK     select-event-mask (*3)
     4     EVENTMASK     forward-event-mask (*4)
     4     EVENTMASK     synchronous-event-mask (*5)

     (*1) Specify the events to be neglected by the IM library via XFilterEvent.
     (*2) Specify the events to be deselected by the IM library with XSelectInput.
     (*3) Specify the events to be selected by the IM library with XSelectInput.
     (*4) Specify all the events to be forwarded to the IM Server by the IM library.
     (*5) Specify the events to be forwarded with synchronous flag on by the IM library.
```

[illegible] XIM_SYNC_REPLY [illegible]

[illegible]

[illegible]

XIM_EXT_FORWARD_KEYEVENT [illegible] XIM_FORWARD_EVENT [illegible]

```
XIM_EXT_FORWARD_KEYEVENT (IM Server <--> IM library)
     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
```

```
     2     BITMASK16     flag
          #0001     synchronous
     2     CARD16     sequence number
     1     BYTE     xEvent.u.u.type
     1     BYTE     keycode
     2     CARD16     state
     4     CARD32     time
     4     CARD32     window
```

XIM_EXT_MOVE[illegible] *6 J[illegible]1"J6$J74?;1[illegible]6[illegible]*6 [illegible]

```
XIM_EXT_MOVE (IM library -> IM Server)

     2     CARD16     input-method-ID
     2     CARD16     input-context-ID
     2     INT16     X
     2     INT16     Y
```

XIM_EXT_MOVE[illegible]C[illegible]

B. Transport List

"[illegible]6 [illegible]

"[illegible]4"2 [illegible]XIM_SERVERS[illegible] [illegible]C[illegible] ?2$4?1[illegible] "54<[illegible]25"[illegible]

```
     "{category=[value,...]}..."
```

"[illegible]

```
server;: IM Server name (used for XIM_SERVERS)
locale;: XPG4 locale name (LOCALES)
transport;: transport-specific name (TRANSPORT)
```

"[illegible]/

TCP/IP Names

"[illegible]#[illegible]/

```
<local name>  ::= "local/"<hostname>":"<pathname>
```

3[illegible]T U[illegible]![illegible]

6 [illegible]G[illegible]T U[illegible]6 [illegible]

"[illegible]#[illegible]6[illegible]/

```
<TCP name>  ::=  "tcp/"<hostname>":"<ipportnumber>
```

[illegible]

```
tcp/expo.lcs.mit.edu:8012
tcp/18.30.0.212:7890
```

DECnet Names

[illegible]

```
<DECnet name>  ::=  "decnet/"<nodename>"::IMSERVER$"<objname>
```

[illegible]

```
DECNET/SRVNOD::IMSERVER$DEFAULT
decnet/44.70::IMSERVER$other
```

X Names

[illegible]

```
<X name>  ::=  "X/"
```

[illegible]

C. Protocol Number

Major Protocol number

XIM_CONNECT	#001
XIM_CONNECT_REPLY	#002
XIM_DISCONNECT	#003
XIM_DISCONNECT_REPLY	#004
XIM_AUTH_REQUIRED	#010
XIM_AUTH_REPLY	#011
XIM_AUTH_NEXT	#012
XIM_AUTH_SETUP	#013
XIM_AUTH_NG	#014
XIM_ERROR	#020
XIM_OPEN	#030
XIM_OPEN_REPLY	#031
XIM_CLOSE	#032

XIM_CLOSE_REPLY	#033
XIM_REGISTER_TRIGGERKEYS	#034
XIM_TRIGGER_NOTIFY	#035
XIM_TRIGGER_NOTIFY_REPLY	#036
XIM_SET_EVENT_MASK	#037
XIM_ENCODING_NEGOTIATION	#038
XIM_ENCODING_NEGOTIATION_REPLY	#039
XIM_QUERY_EXTENSION	#040
XIM_QUERY_EXTENSION_REPLY	#041
XIM_SET_IM_VALUES	#042
XIM_SET_IM_VALUES_REPLY	#043
XIM_GET_IM_VALUES	#044
XIM_GET_IM_VALUES_REPLY	#045
XIM_CREATE_IC	#050
XIM_CREATE_IC_REPLY	#051
XIM_DESTROY_IC	#052
XIM_DESTROY_IC_REPLY	#053
XIM_SET_IC_VALUES	#054
XIM_SET_IC_VALUES_REPLY	#055
XIM_GET_IC_VALUES	#056
XIM_GET_IC_VALUES_REPLY	#057
XIM_SET_IC_FOCUS	#058
XIM_UNSET_IC_FOCUS	#059
XIM_FORWARD_EVENT	#060
XIM_SYNC	#061
XIM_SYNC_REPLY	#062
XIM_COMMIT	#063
XIM_RESET_IC	#064
XIM_RESET_IC_REPLY	#065
XIM_GEOMETRY	#070
XIM_STR_CONVERSION	#071
XIM_STR_CONVERSION_REPLY	#072
XIM_PREEDIT_START	#073
XIM_PREEDIT_START_REPLY	#074
XIM_PREEDIT_DRAW	#075
XIM_PREEDIT_CARET	#076
XIM_PREEDIT_CARET_REPLY	#077
XIM_PREEDIT_DONE	#078
XIM_STATUS_START	#079
XIM_STATUS_DRAW	#080
XIM_STATUS_DONE	#081
XIM_PREEDITSTATE	#082

`(*) The IM Server's extension protocol number should be more than #128.`

D. Implementation Tips

[illegible]

[illegible]

[illegible] `XIM_QUERY_EXTENSION` [illegible] `XIM_EXT_SET_EVENT_MASK` [illegible] `XIM_QUERY_EXTENSION_REPLY` [illegible]

[illegible] `XIM_EXT_SET_EVENT_MASK` [illegible]

[illegible]



[illegible]

[illegible]



[illegible]

[illegible]

[illegible]

[illegible]

[illegible]

[illegible] `XIM_REGISTER_TRIGGERKEYS` [illegible]

[illegible]



[illegible]

[illegible]


IM Library
IM Server
Keys in the on-key-list
XIM_TRIGGER_NOTIFY
Keys in the on-key-list
XIM_EXT_SET_EVENT_MASK
intercept-event-mask is set
the specified events are being filtered
the specified events are being processed
XIM_TRIGGER_NOTIFY_REPLY
Keys in the off-key-list
Keys in the off-key-list
XIM_EXT_SET_EVENT_MASK
select-event-mask is set
the specified events are being processed
the specified events are being discarded

[illegible]

[illegible]

[illegible]

[illegible]

[illegible]

[illegible] [illegible]

[illegible] [illegible]

[illegible] [illegible]

[illegible]

[illegible]

$□□□□□□ □□□□□□□□□□□□□□□□□□□□3□□□□□□□□□□□□□□□□□□□6□□ □□□□□*□□□□ □□□ □□□□□□□□□□□ □□□ □□□□,□□□□□□□ □□□□□□□□□□□□□□□□ □□□□□,□□ □□□□ □□□ □□□□ □□6 □□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□,6 □□□□□□□□□□□□□□□□□□□□□□□□□□□,□

$□□□□□□□□□

6□□4□$□□□□□□ □□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□G□□*6 J□15715 □□□□□□□□□□□□□□□□□□□□□□□□□6 □□□□□□□□□□□□□□□□□□□□□□□□

5□□□□□□□□,"□□□6□□□□□ □□□□□□□□□□□□□□□□□,□□□□□□□□□*6 J□15715□□□□□□

□□□□□3□□□□3□□

□□□□□□□□□□□□□□□□□□		□□□□□□□□□
□□□	□□□□	$□□□□□□ □□□□□□
□J□□□□	□□□□□□	□□□□□□□□□□□□*□3□□□□□□□□□□□□
A□□□	□□□□J□□□□□	□□□□□□□□□□□□*□3□□□□□□□□□□□□
8□□□□□□	Q□□□□□□□	"□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□
3□□□□□	□□□□□□	6 □□3□□□□□□68
4□□□	□□□□□□□□J□□□□	*6□□□□□4□□□+□□□□□□□□□,J*6 J*$2<<1$",□□□□□□□□-
□□□	□□□□□□	(E
□□□□	□□□□□□LKM	□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□68
□□□□	□□□□□□L&M	□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□+Q&-
□□□□	□□□□□□LEM	□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□+Q&-

6□□□+□□□□□□□□□□□□□□□□□□6 □□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□-□□□□□□6 □□□□□□□□□□□□□□□□□□$□□□□□□ □□□G□□□

□□□□□3□□ □3□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□!□□□□□□□□□□□□□□□□□□□

□□□□□□□□□□□□□□□□□□		□□□□□□□□□
□□□	□□□□	$□□□□□□ □□□□□□
□J□□□□	□□□□□□	□□□□□□□□□□□□*□3□□□□□□□□□□□□
A□□□	□□□□J□□□□□	□□□□□□□□□□□□*□3□□□□□□□□□□□□
8□□□□□□	Q□□□□□□□	"□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□
3□□□□□	□□□□□□	□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□68
4□□□	□□□□□□□□J□□□□	*6□□□□□4□□□+□□□□□□□□□,J*6 J*$2<<1$",□□□□□□□□-
□□□	□□□□□□	(E
□□□□	□□□□□□LKM	6 □□□□□□□□□□□□□□□□□□□□□□□□□□□□68
□□□□	□□□□□□L&M	□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□+Q&-
□□□□	□□□□□□LEM	□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□+Q&-
□□□□	□□□□□□L(M	□□□□□□□□□□□□□B□□□□□□□□□□□□$□□□□□□ □□□□□□□□□□□□□□□□□□□□□□□□ +QE-

+Q&-□□□□□□□.□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□

[illegible]

[illegible]

[illegible]		[illegible]
[illegible]	[illegible]	**3**
K	K	[illegible]
	&	[illegible]
	E	[illegible]
&	K	[illegible]
E	K	[illegible]
	&	[illegible]

```
only-CM            :    data is sent via a ClientMessage
multi-CM           :    data is sent via multiple ClientMessages
Property-with-CM   :    data is written in Property, and its Atom
                        is send via ClientMessage
PropertyNotify     :    data is written in Property, and its Atom
                        is send via PropertyNotify
```

[illegible]

- [illegible]

- [illegible]

- [illegible]

[illegible]

[illegible]

[illegible]

[illegible]

[illegible]

[illegible]

[illegible]

[illegible]3[illegible]&[illegible]3[illegible]'[illegible]([illegible])

[illegible]		[illegible]
[illegible]	[illegible]	$[illegible] [illegible]
[illegible]J[illegible]	[illegible]	[illegible]*[illegible]3[illegible]
A[illegible]	[illegible]J[illegible]	[illegible]*[illegible]3[illegible]
8[illegible]	Q[illegible]	"[illegible]
3[illegible]	[illegible]	6 [illegible]68
4[illegible]	[illegible]J[illegible]	*6[illegible]4[illegible]+[illegible],J*6 J 25184"4,[illegible]-
[illegible]	[illegible]	N
[illegible]	[illegible]LEKM	+[illegible].[illegible]84"4[illegible]/[illegible]EK[illegible]-

[illegible]3[illegible]*[illegible]3[illegible]'[illegible]([illegible]![illegible])

[illegible]		[illegible]
[illegible]	[illegible]	$[illegible] [illegible]
[illegible]J[illegible]	[illegible]	[illegible]*[illegible]3[illegible]
A[illegible]	[illegible]J[illegible]	[illegible]*[illegible]3[illegible]
8[illegible]	Q[illegible]	"[illegible]
3[illegible]	[illegible]	6 [illegible]68
4[illegible]	[illegible]J[illegible]	*6[illegible]4[illegible]+[illegible],J*6 J[illegible]52"2$2?,[illegible]-
[illegible]	[illegible]	N
[illegible]	[illegible]LEKM	+[illegible].[illegible]84"4[illegible]/[illegible] 4*[illegible]EK[illegible]-[illegible]+Q&-

+Q&-[illegible]6[illegible]EK[illegible]K[illegible]

[illegible]

6[illegible]3[illegible] "[illegible]

X "[illegible]*$[illegible]4[illegible]6 [illegible]$[illegible] [illegible]

X "[illegible]*$[illegible]4[illegible]6 [illegible]<[illegible]

"[illegible]*$[illegible]/

□□□□□3□□+□3□□□□,□□□□□□□-□□%□□□!□□□□□□'□□□□□□□□

.□□□□□□□□		□□□□□□□□□
8□□□□□□	Q□□□□□□□	"□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□
3□□□□□	□□□□□□□	6 □□□□□□□□□□□□□□□□□□□□□□□□□□□□□68
4□□□	□□□□□□□□□	□□□□.□□□□□□□□□□□□□□□□□□4□□□□+Q&-
4□□□	□□□□	*4J□"56<@
□□□	□□□□□□□	N
□□□	□□□□	□□□□ □□□4□□□□□
□J□□□□	Q□□□□	□□□□.□□□□□□□84"4
□□□	□□□□□□□□□□	□□□□□□□□□□□□84"4

"□□□□□□□□.□□□□□□□□□□□□□□□□□□4"2 □□`XInternAtom`□

,J□□□□□□***,

"□□□ □□□□□□□□ □□□□□□□□□ □□□□ □□□□□□□□□□ □□□□□ □□□□ □□□□□ □□□ □□□□ □□□4□□□□□□ □□□□ □□□□6 □□□+□□□□□□□R□"□□□-□

6□□4□□□□□□□□□□□□□□□□□□□□□□□$□□□□□ □□$□□□□□ □□□□□□□□□□□□□□□□□□□□□□□/

□□□□□3 □□/□3 □□□□ □□□□□□□□□□□□□□□□□□□ □□□□□'□□ □□□□□□□□□ □□□ □□□□□.□□□□ □□ %□□%□□□!

□□□□□□□□□□□□□□□□□□□□		□□□□□□□□□
□□□	□□□□	$□□□□□ □□□□□□
□J□□□□	□□□□□□□	□□□□□□□□□□□□□*□3□□□□□□□□□□□□□□□
A□□□	□□□□J□□□□□	□□□□□□□□□□□□□*□3□□□□□□□□□□□□□□□
8□□□□□□	Q□□□□□□□	"□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□
3□□□□□	□□□□□□□	6 □□□□□□□□□□□□□□□□□□□□□□□□□□□□□68
4□□□	□□□□□□□□J□□□□	*6□□□□□4□□□+□□□□□□□□□,J*6 J□52"2$2?,□□□□□□□-
□□□	□□□□□□□	(E
□□□□	□□□□□□□LKM	□□□□□□□□□□□□□□□□□□.□□□□□□□□□□□□□□□□□□4□□□
□□□□	□□□□□□□L&M	□□□□.□□□□□□□□□□□□□□□□□□□4□□□

□□6 □□□□□□□□□□□□□□□□□□□$□□□□□

$□□□□□ □□□□□□

"□□□□□□□□□□□□□□□□□□□□□□$□□□□□ □□□□□□□□□□□□□□□□□□□□□□□□□□□/

[illegible]3[illegible]0[illegible]3[illegible]'[illegible]([illegible])

[illegible]		[illegible]
[illegible]	[illegible]	$[illegible] [illegible]
[illegible]J[illegible]	[illegible]	[illegible]*[illegible]3[illegible]
A[illegible]	[illegible]J[illegible]	[illegible]*[illegible]3[illegible]
8[illegible]	Q[illegible]	"[illegible]
3[illegible]	[illegible]	[illegible]68
4[illegible]	[illegible]J[illegible]	*6[illegible]4[illegible]+[illegible],J*6 J 25184"4,[illegible]-
[illegible]	[illegible]	N
[illegible]	[illegible]LEKM	+[illegible].[illegible]84"4[illegible]/[illegible]EK[illegible]-

[illegible]3[illegible]1[illegible]3[illegible]'[illegible]([illegible]![illegible])

[illegible]		[illegible]
[illegible]	[illegible]	$[illegible] [illegible]
[illegible]J[illegible]	[illegible]	[illegible]*[illegible]3[illegible]
A[illegible]	[illegible]J[illegible]	[illegible]*[illegible]3[illegible]
8[illegible]	Q[illegible]	"[illegible]
3[illegible]	[illegible]	[illegible]68
4[illegible]	[illegible]J[illegible]	*6[illegible]4[illegible]+[illegible],J*6 J[illegible]52"2$2?,[illegible]-
[illegible]	[illegible]	N
[illegible]	[illegible]LEKM	+[illegible].[illegible]84"4[illegible]/[illegible] 4*[illegible]EK[illegible]-[illegible]+Q&-

+Q&-[illegible]6[illegible]B[illegible]EK[illegible]K[illegible]

[illegible]

6[illegible]3[illegible]
"[illegible]

X "[illegible]*$[illegible]6 [illegible]4[illegible]$[illegible] [illegible]

X "[illegible]*$[illegible]6 [illegible]4[illegible]<[illegible]

"[illegible]*$[illegible]/

□□□□□3□□□2□3□□□□,□□□□□□-□□%□□□!□□□□□□'□□□□□□□□□

.□□□□□□□		□□□□□□□□
8□□□□□□	Q□□□□□□□	"□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□
3□□□□□	□□□□□□	□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□68
4□□□	□□□□□□□□	□□□□.□□□□□□□□□□□□□□□□4□□□□+Q&-
4□□□	□□□□	*4J□"56<@
□□□	□□□□□□	N
□□□	□□□□	□□□□ □□□4□□□□□
□J□□□□	Q□□□□	□□□□.□□□□□□84"4
□□□	□□□□□□□□□	□□□□□□□□□□□84"4

+Q&-□"□□□□□□□□.□□□□□□□□□□□□□□□□□4"2 □□□ □□□□□□□□□□□□□□□□XInternAtom□

"□□□6 □□□□□□□□□□ □□□□□□□□□□□ □□□□□ □□□□□□□□□□□ □□□□□□ □□□□□ □□□□□□ □□□□ □□□□ □□□4□□□□□□□ □□□□□ □□□□ □□□+□□□□□□□R□"□□□-□

6□□4□□□□□□□□□□□□□□□□□□□□□□□□$□□□□□ □□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□$□□□□□ □□□□□□□□□□□□□□ □□□□□□□/

□□□□□3□□□□□3□□□□□□□□□□□□□□□□□□□□□□□□□□□□'□□□□□□□□□□□□□□□□□□□□□.□□□□□□□ %□□%□□□!

□□□□□□□□□□□□□□□□□		□□□□□□□□
□□□	□□□□	$□□□□□ □□□□□□
□J□□□□	□□□□□□	□□□□□□□□□□□□*□3□□□□□□□□□□□□□
A□□□	□□□□J□□□□□	□□□□□□□□□□□□*□3□□□□□□□□□□□□□
8□□□□□□	Q□□□□□□□	"□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□
3□□□□□	□□□□□□	□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□68
4□□□	□□□□□□□J□□□□	*6□□□□□4□□□+□□□□□□□□□,J*6 J□52"2$2?,□□□□□□□-
□□□	□□□□□□	(E
□□□□	□□□□□□LKM	□□□□□□□□□□□□□□□□.□□□□□□□□□□□□□□□□□4"2
□□□□	□□□□□□L&M	□□□□.□□□□□□□□□□□□□□□□□□4"2

$□□□□□□□$□□□□□□□□□

6□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□□6 □□